

Si te has vuelto loco intentando configurarlo, aqui tienes la solución :)

Set aMule's webinterface

This guide will only work with the 2.x-version of the aMule client. All commands stated are to be run in a terminal, such as konsole or gnome-terminal. In most cases you will have to compile aMule yourself if you want amuleweb, if not you can jump directly to *"Configuration of the aMule daemon"* section of this guide.

aMule source code can be grabbed [here](#).

Installation of the aMule daemon

```
Extract and run $ ./configure --enable-amulecmd --enable-webserver --disable-monolithic  
--enable-amule-daemon --prefix=/home/  
$ make  
$ make install  
where the --prefix= parameter is to be replaced with the path of where amule is to be installed.
```

If you wish to install the client system-wide, rather than the user's own home directory, the '--prefix=' parameter can be removed.

Configuration of the aMule-daemon

Go to the path where aMule was installed, which in our case is *~/bin* and run *./amuled*. When this is done, the configuration file *~/.aMule/amule.conf* is created.

Quit the daemon again. Find and replace the following lines in *~/.aMule/amule.conf*.

- AcceptExternalConnections=1 <-- To let aMule listen to external connections.
- ECPassword=56f491c56340a6fa5c158863c6bfb39f <-- MD5 of the password you wish to use.

Use the command *md5sum* to create a MD5-string of a password:

```
$ echo -n password | md5sum  
56f491c56340a6fa5c158863c6bfb39f -
```

Configuration of the aMule web interface

The program *amuleweb* is used to get the web interface running. To create a configuration file for this program, the following parameters are used, where *--password* is the password used in the amule daemon configuration and *--admin-pass*

is the password to access the web interface itself. `$./amuleweb --write-config --host=localhost --password=password --admin-pass=anotherpassword`

Then you just have to start *amuleweb*, and you're done. Be aware that the amule daemon must be running.

```
$ ./amuleweb
```

Connecting from your web browser

Go to the web address <http://hostname:4711>, where *hostname* is the name of the computer running *amuleweb* and 4711 is the port *amuleweb* is using. In most cases this should be <http://localhost:4711>.